



QUARTERDECK®

3.5" disks



Offer at End
of Manual



Partition·It™

User Guide

Vip # 335 7320



QUARTERDECK®

3.5" disks



Offer at End
of Manual



Partition-It™

User Guide

500US-PI0100

Partition-It User Guide

© 1996, Quarterdeck Corporation. All rights reserved. You may not copy, modify, or translate this manual or any part of this manual, or reduce any part of it to any machine-readable form.

Documentation Credits

Management: Phil Glosserman

Writing: Bill von Hagen

Technical Editing: Gareth Boulton, Jeff Hyman, Elliot Lowe

Editing: Phil Glosserman

Design: Sharon Lettvin, Scott Harrell

Illustration: Jefferson Ballew, Bill von Hagen

Layout: Bill von Hagen

Online Help: Bill von Hagen

TRADEMARKS

Quarterdeck is a registered trademark, and the Quarterdeck "Q" symbol and Partition-It are trademarks of Quarterdeck Corporation or its subsidiaries. All other trademarks and registered trademarks are trademarks or registered trademarks of their respective holders.

Quarterdeck Corporation
13160 Mindanao Way
Marina del Rey, CA 90292-9705

Product Information (800) 683-6696 Fax: (813) 523-2391 info@quarterdeck.com
World Wide Web <http://www.quarterdeck.com/>

For technical support information, see the Technical Support appendix at the end of this manual.

END USER LICENSE AGREEMENT

NOTICE: Please read this End User License Agreement (this "Agreement"). If you install or use the enclosed software product (the "Software"), you will be legally bound by this Agreement. If you do not want to be bound, you must promptly return the Software, all accompanying documentation, and all other accompanying written materials in the original packaging to the location where you obtained them for a full refund. If you do not accept this Agreement, you may not copy, retain or use the Software.

1. **License Grant.** Quarterdeck Corporation ("Quarterdeck") grants you a nonexclusive license to use the Software, as follows:

Except as stated below, you may install the Software on only one computer. If the Software may be used from any computer or terminal other than the computer on which it is installed (whether because the computer on which it is installed is part of a network or for any other reason), you must license a copy of the Software for each computer or terminal from which the Software may be used. For example, if ten computers or terminals have access to the Software on your network, then you must license ten copies of the Software solely for use on that network. However, multiple users may share the Software to work collaboratively on the same document or data at the same time without licensing multiple copies so long as the Software is resident on only one computer and may not otherwise be used from another computer or terminal.

If you regularly use more than one computer (such as an office computer and a home computer), you may install the Software on each of them so long as the Software is never used on more than one of the computers at the same time. If you want to allow the Software to be used on more than one computer at the same time, then you must license a copy of the Software for each computer.

You may make a reasonable number of back-up copies of the Software. The back-up copies may be used only to replace an unusable copy of the Software. You must destroy any copies of the Software that are replaced by a back-up copy. Back-up copies must include all proprietary rights notices appearing on the original and must remain in your possession or control.

Except as specifically permitted in this Agreement, you may not (i) copy the Software or this manual, (ii) modify the Software or separate out any of its components for use with other software (except to the extent contemplated in the enclosed user documentation) (iii) use the Software to provide time sharing, service bureau or similar services, or (iv) decompile, disassemble, or otherwise reverse engineer the Software. Further, you may not allow anyone to do anything that this Agreement prohibits you from doing.

You understand that the Software is licensed to you and not sold. Quarterdeck retains title to all copies of the Software.

2. **Limited Warranties and Disclaimer.** (a) Quarterdeck warrants that, for ninety (90) days after you obtain the Software (the "Warranty Period"), (i) the Software will operate as stated in the enclosed user documentation, and (ii) the disk or other media on which the Software is provided will be free of defects in material or workmanship. This limited warranty does not cover anything caused by accident or abuse or by use of the Software other than for its reasonably intended purposes and as recommended in the accompanying user documentation. Also, Quarterdeck does not warrant that the operation of the Software will be uninterrupted or error free. This warranty gives you specific legal rights, and you may also have other rights which vary from state to state.

(b) *Except as stated in Section 2(a), Quarterdeck does not make any warranties. In particular, Quarterdeck disclaims all implied warranties, including the implied warranties of merchantability, fitness for a particular purpose, and non-infringement. The duration of any implied warranty that is not effectively disclaimed will be limited to the 90 day Warranty Period. Some states do not apply limitations on how long an implied warranty lasts, so the above limitation may not apply to you.*

3. **Exclusive Remedies.** (a) If, during the Warranty Period, you report any breach of warranty to Quarterdeck and Quarterdeck is reasonably able to verify that breach, Quarterdeck will, at its option, either (i) correct the Software or replace any defective media, (ii) help you work around or avoid the problem, or (iii) allow you to return the Software, all accompanying documentation, and all other accompanying written materials in the original packaging for a full refund. If you return the Software for a refund, you may not retain or use the Software, and you must immediately destroy all back-up copies and any other copies of the Software in your possession or control.

(b) During the Warranty Period, you may report breaches of warranty over the phone by calling (800) 354-3222 or by letter addressed to Quarterdeck Corp., 5770 Roosevelt Blvd. Building 400, Clearwater, FL 34620, Attention: Customer Service. You must describe the breach in detail and include a phone number or address at which you can be reached during normal business hours. Quarterdeck will respond within a reasonable time to any reported breach. You must pay all costs of shipping any Software or other materials from you to Quarterdeck and from Quarterdeck to you. Any corrected or replaced software that you obtain under this Agreement will be considered part of the Software licensed under this Agreement and will be covered by warranty only for any time remaining in the original Warranty Period.

(c) **The remedies stated in this Section 3 are your only rights or remedies, and will be Quarterdeck's only liability or obligation, for any breach by Quarterdeck of any warranty.**

4. Proprietary Rights. Quarterdeck and its licensors retain all copyrights, trade secret rights, patents, trademarks, and any other proprietary rights covering or relating to the Software. You acknowledge that the Software includes or incorporates proprietary and confidential information belonging to Quarterdeck and/or its licensors. All rights not expressly granted by Quarterdeck in this Agreement are reserved.

5. No Consequential Damages; Limitation of Liability. *Neither Quarterdeck nor its licensors will be liable for any special, incidental, consequential or exemplary damages, including without limitation damages for loss of use, lost profits or loss of data or information of any kind, arising out of or in connection with the Software or its use or this Agreement, even if Quarterdeck or its licensor have been advised of the possibility of such damages. In no event will Quarterdeck's or its licensors' liability for any claim relating to the Software or its use or this Agreement, whether in contract, tort or any other theory of liability, exceed the license fee paid by you. Some states do not allow the exclusion or limitation of incidental or consequential damages, so the above limitation or exclusion may not apply to you.*

6. Limits on Your Right to Transfer. You may not sublicense, rent, lease, lend, sell, grant a security interest in, or otherwise transfer the Software or any rights under this Agreement, except that you may transfer your copy of the Software if: (i) you transfer to the same person all copies of the Software and of any accompanying documentation in your possession or control, (ii) that person agrees in writing to assume all of your obligations under and otherwise to be bound by this Agreement, and (iii) you notify Quarterdeck at the address or phone number specified below of the transfer of the Software, including the name, address and phone number of the new user of the Software and the serial number of the Software. Your rights under this Section 6 only apply to incidental transfers. No right is granted to transfer or in any way distribute multiple copies of the Software in connection with a trade or business (whether as a value added reseller, OEM, distributor, systems integrator, or otherwise).

7. Export. You acknowledge that the Software is subject to United States export control laws, including the export administration regulations. You will not export, re-export or divert the Software in contravention of those laws.

8. Termination. Quarterdeck may terminate this Agreement if you violate it. You must destroy all copies of the Software in your possession or control promptly upon termination. Upon Quarterdeck's request, you must certify in writing that you have complied with your obligations under this Section 8

and otherwise under this Agreement. Termination by Quarterdeck will not limit any of its other rights or remedies under this Agreement or at law or in equity. Any provision of this Agreement that by its sense and context is intended to survive termination of this Agreement will survive termination.

9. Severability. If any provision of this Agreement is illegal or unenforceable under applicable law, the remaining provisions of this Agreement will remain valid and fully enforceable. If any provision is in part enforceable and in part unenforceable, it will be enforced to the extent permitted under applicable law.

10. U.S. Government Restricted Rights. If this product is licensed by a DoD agency, such agency's rights in this product are governed by the restrictions in the Technical Data -- Commercial Items clause at DFARS 252.227-7015 and DFARS 227.7202, or any successor regulation. If this product is licensed by any other agency or instrumentality of the United States of America, use, duplication and disclosure are subject to restriction as set forth in subparagraphs (a) - (d) of the rights in Technical Data and Computer Software clause at FAR 52.227-19 or any successor regulation.

11. Governing Law. This Agreement is governed by California law.

12. Entire Agreement. This Agreement, together with any special rights or promotions provided in writing with your copy of the Software, is the entire agreement between you and Quarterdeck relating to the Software. It supersedes any prior or contemporaneous oral or written communication relating to the Software.

Questions? Write: Quarterdeck Corporation, 13160 Mindanao Way, Marina del Rey, CA 90292-9705.
Phone: (310) 309-3700 Fax: (310) 309-4218.



Contents

Introduction	1
Basic Concepts	1
Introduction to Disk Partitions	2
Introduction to Clusters and Cluster Size	3
Limitations of DOS and Windows Utilities	5
How Partition-It Helps You Optimize Your Hard Drives	6
Advanced Disk Drive Concepts	6
System Requirements	11
About This Guide	11
 Chapter 1: Installing and Starting Partition-It	13
Installing Partition-It Under Windows 95	13
Installing Partition-It Under Windows 3.1x	14
Starting Partition-It	15
Resolving Problems Starting Partition-It	16
Using Partition-It	18
Viewing Drives and Partitions in Partition-It	19
 Chapter 2: Optimizing Performance with Partition-It ..	23
Creating Multiple Partitions to Reclaim Disk Space	23
Changing the Cluster Size on Existing Partitions	25
Creating a Separate Partition for Virtual Memory Files	28
Creating a Swap Partition Under Windows 3.1x	30
Creating a Swap Partition Under Windows 95	32
 Chapter 3: Basic Partition-It Operations	35
Getting Information About a Disk or Partition	35
Resizing a Partition	36
Creating a Partition	39



Rules for Creating Partitions	43
Deleting a Partition	44
Moving a Partition	45
Moving Applications	46
Chapter 4: Advanced Operations	57
Creating and Using Partition-It Recovery Disks	57
Setting Advanced Partition Attributes	59
Hiding a Partition	60
Making a Hidden Partition Visible	61
Marking a Partition as Active	61
Using Partition-It's Advanced Dialogs	62
Using the Advanced Create Partition Dialog	63
Using the Advanced Resize Partition Dialog	64
Changing the Location of Move-It Backup Files	66
Hardware Issues for Partition-It	67
Using Partition-It With Other Operating Systems	67
Using Partition-It on Systems That Also Run Windows NT...	68
Using Partition-It on Systems That Also Run OS/2	68
Using Partition-It with other Utility Programs	69
Anti-Virus Software	69
Norton Disk Doctor and Norton Anti Virus	69
Appendix A: Quarterdeck Technical Support	73
1-800-ROBOTECH—Free automated support	73
Q/FAX—Technical Bulletins and Product Information by Fax	73
Quarterdeck Bulletin Board System	74
Talk to a Technical Support Representative	74
Online Technical Support via CompuServe	74
Quarterdeck's World Wide Web Site	74
Quarterdeck's FTP Site	74
Glossary	75
Index	81



Introduction

Welcome to Quarterdeck Partition-It, a revolutionary new hard drive optimization and management tool for Microsoft Windows 95 and Windows 3.1x.

Partition-It can help you:

- ▼ Increase the amount of data you can store on your hard drive without using disk compression software.
- ▼ Increase the speed at which your hard drive can access data.
- ▼ Organize data on your hard drive more efficiently, making it easier to find specific files.
- ▼ Move applications to other locations or hard drives without requiring you to edit a single INI file or registry entry.

Most importantly, you do not have to be a computer wizard to use Partition-It. Partition-It guides you step by step through various ways of optimizing your hard disk.



Throughout this manual, we use the term Windows 3.1x to refer to Windows 3.1, 3.11, and any version of Windows for Workgroups.

Basic Concepts

This section introduces some basic concepts to illustrate how Partition-It works. If you are already familiar with disk partitions, skip to "How Partition-It Helps You Optimize Your Hard Drives" on page 6.



Introduction to Disk Partitions

In using your computer, you have become familiar with the letters associated with various hard and floppy drives. A: typically represents a floppy drive, and C: is typically the hard drive from which you boot your computer.

Since the data on your computer is stored in files, a good way to think of the drive letters on your computer is to visualize them as representing file drawers in which your files are stored. Since simply throwing all of your files into a single file drawer makes it hard to locate or identify a specific file, DOS and Windows let you use directories to provide a further level of organization, just like different folders help you organize information in a filing cabinet.

Even folders can become hard to work with as you accumulate more and more folders and files on your system. Each time you want to locate a specific file, you have to find the appropriate folder, then search through that folder for the right file. If you add additional, larger hard drives, finding files can become even more difficult.

To make it easier to work with large hard drives and greater numbers of folders and files, DOS and Windows let you subdivide your hard drive into additional **partitions**. Partitions are like additional drawers in a filing cabinet—they provide additional, logical ways of dividing up the space you already have and using it more efficiently. Partitions help you access your files more efficiently in two primary ways:

- ▼ by providing an additional level for organizing data on your hard drive, partitions can make it easier to find a specific file or application.
- ▼ by speeding up access to specific files or folders. If you create multiple partitions on a single hard drive, each partition is smaller than the total amount of space available on your hard drive. Your computer can usually locate information in a small partition faster than if it has to search your entire hard drive.

Most hard drives consist of a single partition which is named C: . If you add other drives to your system, they are named D:, E:, and so on. Each partition on your hard drive is associated with a letter just like the drives themselves. The letters that are initially associated with the hard and floppy drives in your computer actually refer to single, large partitions that represent all of the space available on those drives. You've already been using partitions, and may not even have known it!

If your computer already has a C drive and you use Partition-It to create two partitions on that drive, you can access these through the letters C: and D:. If you already had a D drive in your computer, the new partition on your C drive becomes drive E. DOS and Windows assign drive letters to primary partitions on different hard drives before assigning drive letters to other partitions on those drives.

Unfortunately, while partitions are a fairly easy concept to understand, the tools provided by DOS and Windows to work with them are not so simple. That is where Partition-It comes in.

Introduction to Clusters and Cluster Size

When you format a floppy drive, hard drive, or partition using standard DOS utilities, the format utility creates a **file system**. A file system is a computer's way of pre-organizing the disk space on a partition so that it can be used more efficiently, just like notebook paper comes with lines already drawn on it.

In DOS or Windows, disk space in a partition is organized into **clusters**, that are like the sheets of paper on which your files are written. DOS and Windows systems can allocate a maximum of 65,536 clusters on a partition, regardless of its size. However, clusters can vary in size; because all partitions have the same maximum number of clusters, the larger the partition, the larger the cluster size.

Since your computer can allocate up to 65,536 clusters on each partition, the clusters on a 100 megabyte partition can be much smaller than those on a one gigabyte partition. Table 1



shows the cluster sizes associated with partitions of different sizes (partition size given in megabytes):

Table 1: Cluster Sizes on Different Disk Partitions

PARTITION SIZE	CLUSTER SIZE
1 - 31 MB	512 byte
32 - 63 MB	1 K
64 - 127 MB	2 K
128 - 255 MB	4 K
256 - 511 MB	8 K
512 - 1023 MB	16 K
1024 - 2047 MB	32 K

Larger partitions can lead to wasted space on a drive. Although a file can span multiple clusters, each cluster can only be used by a single file. Suppose you have a one gigabyte partition that uses 32K clusters, and you have a file that is exactly 32K in size. If you add a single extra character to that file, the computer must allocate an entire cluster (32K) to hold that character.

Dividing a large disk drive into multiple partitions is an easy way to maximize the use of space on the drive. If you add a single character to that file on a 100 megabyte partition that uses 2K clusters, the computer need only allocate an additional 2K to hold that character. While still somewhat wasteful, using a smaller partition and cluster size saves you 30K! Multiply this by the number of files you have on your computer, and you can see that using partition sizes that are larger than necessary can waste a significant amount of space on a hard drive.

Table 2 shows a real example of the extra space required to install an application on partitions of different sizes, based on installing Microsoft Office 95. The total size of Microsoft Office 95 at the time this document was written was 99.93 megabytes. The last column shows the amount of space you would

save by using a smaller cluster size (shown in the Cluster Size column), as opposed to a cluster size of 32 K.

Table 2: Disk Space Used by Microsoft Office on Different Partition Sizes

PARTITION SIZE	CLUSTER SIZE	SPACE USED	WASTED SPACE	POTENTIAL SAVINGS
1024 - 2047 MB	32 K	120.28 MB	20.26 MB	(N/A)
512 - 1023 MB	16 K	109.45 MB	9.52 MB	10.84 MB
256 - 511 MB	8 K	104.23 MB	4.30 MB	16.05 MB
128 - 255 MB	4 K	102.02 MB	2.09 MB	18.26 MB
101 - 127 MB	2 K	100.89 MB	0.96 MB	19.39 MB

If you have very large files, a large cluster size allows you to store your files on fewer clusters. This can improve performance when accessing these files. However, a large cluster size will waste disk space if you have many files that are smaller than the cluster size.

Limitations of DOS and Windows Utilities

DOS and Windows include a utility, FDISK.EXE, for working with partitions. To create or modify partitions on your system using FDISK, you must reformat your hard disk, destroying all of the information on your system. This means that you have to back up your hard drive before you can modify partitions. After creating or modifying partitions, you have to restore all of the data from your backups. Usually, you must also reinstall any Windows applications that you want to move to a different partition, because all of your existing INI file and registry entries for those applications point to the original partition. In addition, DOS and Windows do not provide any way of modifying the cluster size within a partition—the FDISK utility automatically selects the cluster size when a partition is created.



How Partition-It Helps You Optimize Your Hard Drives

Partition-It provides a consistent, graphical interface that lets you see all of your drives, view the partitions and free space on those drives, and optimize those partitions by pointing and clicking. With Partition-It, you can:

- ▼ **resize** clusters to use the available space on a partition more efficiently, decreasing cluster size to reclaim wasted space or increasing it to suit the types of files stored on that partition.
- ▼ **create** additional partitions to improve the organization of, and help speed up access to, the information on your system.
- ▼ **move** partitions to reorganize the free space on your drives, so you can increase the size of existing partitions, if necessary.
- ▼ **delete** partitions to provide free space into which you can move other partitions or increase their sizes.
- ▼ **resize** partitions so you can store more information on them or so that you can use a different cluster size to optimize their storage capacity.
- ▼ **move** applications to other partitions to free space on existing partitions.

Advanced Disk Drive Concepts

This section discusses more complex partitioning concepts for advanced users—it is not necessary to read this section to use Partition-It.

Different Types of Partitions

DOS and Windows let you create a maximum of four physical partitions on a disk. A maximum of four partitions on a disk was fine when disk sizes were smaller, but may not be very efficient on today's systems, where disk drive sizes of one gigabyte and greater are common. To get around this limitation,

you can identify one partition as an "extended" partition, in which you can subsequently create additional, **logical partitions**. Logical partitions do not occupy a specific portion of your disk, but exist within other (extended) partitions.

Systems running DOS, Windows 3.1x, and Windows 95 recognize and use several different types of partitions:

- ▼ **primary**—a physical portion of your disk from which DOS, Windows 3.1x, or Windows 95 can boot when you start or restart your computer. Your C drive is always a primary partition.
- ▼ **extended**—a physical partition that can be divided into multiple, logical sections that your operating system will see as partitions. An extended partition can not contain boot information, since this type of partition is only recognized *after* you have booted an operating system.
- ▼ **logical**—a portion of an extended partition that the operating system recognizes as an actual partition. Logical partitions can only be identified by your system after the extended partitions in which they are located are identified. Logical partitions cannot contain boot information for your system.

Primary, extended, and logical partitions are known as FAT (File Allocation Table) file systems because your system maintains a table to find information within those partitions. This table is composed of records that identify the files in the partitions and the blocks of data associated with those files. These records have different sizes, depending on the size of the partition. Partitions between 0 and 15 megabytes (typically used with older systems) can use a file allocation table called FAT12, because a data address of 12 bits was sufficient to find a file and its starting location on partitions which were that small. Most current file allocation tables are called FAT16 because they use 16-bit records to locate a file and its starting location. Future updates to Windows 95 will support the FAT32 file allocation table, enabling those systems to automatically find files and their starting locations in even larger partitions. All of the examples of partition and cluster size used in this document



refer to FAT16 cluster sizes, because FAT12 partitions are generally too small to be of much use with today's applications.



Microsoft's FAT32 FAT type was not available when this manual went to press. The FAT32 FAT type will support larger physical partitions on large hard drives by using 32-bit records for drive addressing. Until this FAT type is available, you will probably not need to use the New FAT Type options provided in Partition-It's Create, Resize Cluster, and Resize Partition dialogs, since the FAT16 FAT type is currently used on all partitions larger than 30 MB. Once FAT32 is available, these options will become much more useful, because systems with very large drives could have different FAT types on the same drive.

Using Other Types of Partitions

PCs can run many different operating systems, such as DOS, Windows 95, Windows NT, Novell NetWare, OS/2, versions of UNIX such as Linux, SCO, and NetBSD, and many others. Each of these operating systems uses a different partition format to obtain maximum performance for that specific operating system. Since some users run different operating systems on the same PC, it is necessary to be able to identify the characteristics of each partition on your system. Partitions are assigned a specific numeric type that identifies them to applications, operating systems, and utilities such as Partition-It. This makes it easy for applications and other operating systems to determine whether they can effectively use the data stored in specific partitions.

Partition-It is specifically designed to help you optimize the performance of partitions on a DOS, Windows 3.1x, or Windows 95 PC. Partition-It immediately identifies partitions used by other operating systems, and prevents certain operations that would damage them (such as changing cluster size). In addition, Partition-It lets you create new partitions for use with other operating systems. Partition-It will not format these for

you, but can quickly and easily create them so that you can use them with other operating systems.



For more information on creating partitions of different types, see "Creating a Partition" on page 39.

Disk Fragmentation


Using Partition-It to divide your disk into smaller partitions can help increase system speed by reducing the size of the areas on your disk that your system must search to locate specific files and directories. This section explains why file access can become less efficient as you create and delete files on your system over time.

When writing a file to your disk, DOS or Windows tries to write it as efficiently as possible. At a low level, DOS or Windows tries to write your files to adjacent clusters on your disk, so that it can subsequently read this information as quickly as possible. However, as you write, update, and delete files from your disk, the data on your disk becomes more scattered. This is called **fragmentation**. As an example, consider five adjacent disk clusters and the following scenario:


- ▼ You create file1, which completely fills the first disk cluster.
- ▼ You create file2, which completely fills the second disk cluster.
- ▼ You edit file1 and expand it. The file system allocates additional space for the expanded file in the third disk cluster, since the second cluster is already used by file2.
- ▼ You edit file2 and expand it. The file system allocates additional space for the expanded file in the fourth disk cluster, since the third cluster is already used by file1.
- ▼ You edit file1 and expand it. The file system allocates additional space for the expanded file in the fifth disk




cluster, since the fourth cluster is already used by file2. The clusters now look something like this:



- ▼ You delete file2, causing the clusters to look something like this:



- ▼ You edit file1 and expand it. The file system allocates additional space for the expanded file in the second disk cluster, since that is now the first available free cluster on the disk. The clusters now look something like this:



It is easy to see how fragmentation can slow down your disk by forcing it to work harder to locate the clusters associated with a specific file. If the clusters that contain the data for a single file are spread out all over the disk, your disk drive has to do extra work to move to those locations and read the data. Using Partition-It can help minimize fragmentation by allowing you to use smaller partitions. Smaller partitions reduce the maximum amount of time that your disk must spend looking

for information on a specific partition, since the partition is smaller and is therefore easier to search.

To resolve fragmentation problems in an existing partition, you can use the **Disk Defragmenter** utility provided with DOS versions greater than 6.0 and with Windows 95. This utility optimizes the organization of the information on your hard drive, reducing the amount of time it takes to read and write data to your disk.



For more information on the Disk Defragmenter utility, see your DOS or Microsoft Windows documentation.

System Requirements

Partition-It has the following system requirements:

- ▼ IBM PC, PS/2, or 100% compatible computer with an 80386 DX, i486, 80486, AMD or Cyrix 586 or 686, or Pentium processor.
- ▼ a minimum of 4 megabytes of RAM (8 megabytes are recommended).
- ▼ 3 megabytes of free hard-disk space for installation on Windows 95 systems or 6 megabytes on Windows 3.1x systems.
- ▼ Microsoft Windows 3.1, Windows for Workgroups 3.11, or Windows 95.

About This Guide

This user guide is organized as follows:

- ▼ **Chapter 1, Installing and Starting Partition-It**—explains how to install Partition-It.
- ▼ **Chapter 2, Optimizing Performance with Partition-It**—discusses how to use Partition-It to enhance system performance.



- ▼ **Chapter 3, Basic Partition-It Operations**—provides a reference for Partition-It's basic operations.
- ▼ **Chapter 4, Advanced Operations**—discusses advanced features, such as hiding partitions and making partitions active. This chapter also discusses using Partition-It with other disk-related utilities and with partitions used by other operating systems.
- ▼ **Appendix A, Quarterdeck Technical Support**—explains how to obtain technical support from Quarterdeck if you have questions when using Partition-It.
- ▼ **Glossary**—defines technical terms used in this manual.



Installing and Starting Partition-It



A version of Partition-It on 3.5" disks is available by request. For more information, see the floppy disk offer at the end of this manual.

Installing Partition-It Under Windows 95

To install Partition-It under Windows 95:

- 1 Start Microsoft Windows 95.
- 2 Insert the Partition-It CD-ROM into your CD-ROM drive.
- 3 Click the **Start** button and point to **Settings**. From the Settings menu, select **Control Panel**.
The Windows 95 Control Panel displays.
- 4 Double-click the **Add/Remove Programs** icon.
The Add/Remove Program dialog displays.
- 5 Click **Install**.
The "Install Program from Floppy Disk or CD-ROM" dialog displays.
- 6 Once Windows 95 locates the setup program on your CD-ROM disk, click **Finish**.
- 7 The rest of the installation is easy—just follow the on-screen instructions. When you are ready to go to the next screen, click the **Next** button.

When you see the Create Recovery disk dialog, please create a recovery disk. If you do not choose to create a



Partition-It recovery disk during installation, please see "Creating and Using Partition-It Recovery Disks" on page 57 before using Partition-It.



We strongly suggest that you create a recovery disk for Partition-It before using any Partition-It functions. If you experience a system failure while using any Partition-It operation, **you must not let your system restart from the hard drive**. Turn your machine off, locate the Partition-It recovery disk, and restart your system from the floppy disk.

Installing Partition-It Under Windows 3.1x

To install Partition-It under Windows 3.1x:

- 1 Start Microsoft Windows 3.1x.
- 2 Insert the Partition-It CD-ROM into your drive.
- 3 In the Program or File manager, select the **Run** command from the File menu.
The Run dialog displays.
- 4 Type **x:\SETUP** (substitute the letter of your CD-ROM drive for x) and press enter.
- 5 The rest of the installation is easy—just follow the on-screen instructions. When you are ready to go to the next screen, click the **Next** button.



If the correct version of the Windows 3.1x 32-bit extensions (WIN32S) cannot be found on your system, Partition-It's setup procedure automatically installs the necessary files. In this case, setup displays a message telling you to reboot your machine once the installation is complete.

When you see the Create Recovery disk dialog, we suggest you create a recovery disk.



When you see the Create Recovery Disk dialog, we strongly suggest that you create a recovery disk. It's a good precautionary measure to have a recovery disk before using any Partition-It function. If you experience a system failure while using any Partition-It operation, **you must not let your system restart from the hard drive**. For information, see "Creating and Using Partition-It Recovery Disks" on page 57.


Starting Partition-It

To start Partition-It:

- ◆ On Windows 95 systems, click the **Start** button and point to **Programs**. In the Programs submenu, select **Quarterdeck Partition-It**, then click **Partition-It**.

On Windows 3.1x systems, double-click the **Partition-It** icon in the Partition-It program group.

The main Partition-It screen displays:





By default, Partition-It displays a graphical view of a single drive in the left pane of its main screen. To see a hierarchical view of all of the drives in your system, use Partition-It's Tree view, as explained in "Viewing Drives and Partitions in Partition-It" on page 19.

Resolving Problems Starting Partition-It

Partition-It will not run if any of the drives in a Windows 95 system are running in MS-DOS compatibility mode. This may be the case if:

- ▼ some of your hardware was not correctly identified or is not supported by Windows 95
- ▼ other hardware in your system conflicts with your hard disk controller
- ▼ any of your hardware drivers are not completely Windows 95 compatible.
- ▼ a virus is present in your system.

To resolve MS-DOS compatibility problems:

- 1 Go to the Windows Control Panel and select the **System** icon. Use the Performance tab to identify the drive that is using MS-DOS compatibility mode, and why.

If the driver responsible for MS-DOS compatibility mode is MBRINT13.SYS, you may be running disk-geometry translation software that is intended for use with Windows 3.1x or you may have a boot sector virus. If you are running software that came with your disk drive, try commenting it out of your CONFIG.SYS file, restarting your system, and rerunning Partition-It.



If you have access to the World Wide Web and need to run your hard disk vendor's disk management software, check <http://www.microsoft.com> for Windows 95 compatibility information.

If this does not resolve the problem, run virus detection software on your system before proceeding. If this does not resolve the problem, proceed to the next step.

- 2 Check the Device Manager in the Control Panel's System icon to verify that your hard drive controller is listed. If it is not listed, select the Control Panel's **Add New Hardware** icon. Do not let it search for your controller, and select your controller from the hardware list. If your controller is not listed, contact the manufacturers of the disk controller for a Windows 95 compatible (or 32-bit Windows 3.1x) driver.
- 3 If the line "device=Mh32bit.386" is present in your SYSTEM.INI file, you are using an incompatible driver—comment out this line by proceeding it with a semicolon and try restarting your system.
- 4 If your hard disk controller is listed but displays a yellow exclamation mark, there is a DMA, I/O, IRQ, or memory conflict with another device or driver, or the protected-mode driver for this card is missing or damaged. Verify that the **Disable all 32-bit protected-mode disk drivers** check box is not selected on the File System tab of the System Icon's File System item. If this is not selected, resolve the hardware conflict using the information provided with your hard disk controller.
- 5 Restart Windows 95 and press **F8** at the "Starting Windows 95" prompt. Select item 2, "Logged" boot. After your system boots, check the BOOTLOG.TXT file in your WINDOWS directory to determine which driver did not start correctly.
- 6 If the drive controlled by the problematic disk controller shows an INITCOMPLETESUCCESS message, check the IOS.LOG file in your WINDOWS directory. This file is created if any of your drives are using MS-DOS compatibility mode. Contact Microsoft Product Support and provide them with the first few lines of this file.



- 7 Check to make sure that the protected-mode driver for your disk controller is not damaged. For ESDI and IDE drives, the driver is the file ESDI_506.PDR in the IOSUBSYS subdirectory of your Windows directory. For SCSI controllers, the driver is the file SCSIPTOP.DR in the same directory. To verify these drivers, rerun the Windows 95 Setup application and select the **Verify** option.

If none of the steps listed above resolve the problem and allow you to start Partition-It, your hard drive or controller may be incompatible with Windows 95. If you cannot get Windows 95 or 32-bit Windows 3.1x drivers from the manufacturer, you may need to replace your hard drive controller with a Windows 95-compatible controller. This will enable Windows 95 to efficiently address your hard drive and will also enable you to use Partition-It to maximize your hard drive's performance and storage capability.

Using Partition-It

Partition-It provides three ways to access commands:

- ▼ use the icons on the toolbar at the top of the screen. As you move the cursor over any icon on the toolbar, an explanation of that icon displays at the bottom of the main Partition-It window. See Table 3 on page 19 for an explanation of each icon in Partition-It's toolbar.
- ▼ select commands from the menus at the top of the window.
- ▼ position the cursor over the desired drive or partition in the left pane of the main Partition-It screen and right-clicking to display a menu of available commands (Windows 95 only).



Partition-It will only let you select those toolbar icons or menu commands that are valid for the item that is currently selected in the main Partition-It screen.

Table 3: Toolbar Icons in Partition-It

ICON	PARTITION-IT FEATURE
	Creates a new partition in selected free space.
	Deletes the selected partition.
	Moves the selected partition.
	Resizes the selected partition.
	Resizes clusters in the selected partition.
	Moves applications.
	Provides context-sensitive help for Partition-It icons, commands, buttons and dialogs.


Viewing Drives and Partitions in Partition-It

Partition-It provides two different ways of viewing the drives in your system: hierarchically, using a tree view, or graphically.

Partition-It's graphical view provides a graphical representation of a single drive in your system. Fixed Disk 1 in your sys-



tem is shown by default when you start Partition-It. Here is an example of a graphical view of Fixed Disk 2 in a system:



Different colors are used for different kinds of partitions, as indicated in the following table.

Table 4: Partition Color Codes

blue	existing partition
cyan (light blue)	free space
brown	HPFS (OS/2)
dark red	NTFS (Windows NT)
red	FAT-32




When using Partition-It's graphical display, extended partitions are shown with a dark border to differentiate them from primary partitions.

To see a graphical view of another drive when using Partition-It's graphical view:

- ◆ Select that drive from the pull-down list at the left of Partition-It's toolbar.

A **tree view** lists all of the drives in your system and the partitions they contain, and provides summary information about the names and sizes of those partitions. Here is a sample tree view:



To activate Partition-It's tree view:

- ◆ Select the **Tree View** command from the **Preferences** menu.



Optimizing Performance with Partition-It

In this chapter you will learn how to:

- ▼ Create additional partitions to improve storage capacity and performance.
- ▼ Change the cluster size on existing partitions to increase the amount of data you can store on those partitions.
- ▼ Improve Windows performance by creating a separate partition for virtual memory files.

Creating Multiple Partitions to Reclaim Disk Space

As discussed in "Introduction to Clusters and Cluster Size" on page 3, partitions of different sizes store information in different-sized chunks, which can waste disk space on larger partitions. This section describes how to reclaim wasted space from larger drives by dividing those drives into multiple, smaller partitions. Decreasing partition size can also increase performance by limiting disk fragmentation and improving relative access times for data within a partition.

Suppose you have a relatively large hard drive (greater than 540 MB), partitioned into a single large partition. As explained in "Introduction to Clusters and Cluster Size" on page 3, the smallest amount of disk space (the cluster size) that DOS or Windows can allocate on a drive of this size is 16K if your drive is smaller than one GB, or 32K if your drive is one GB or larger. Each time you increase a file by one byte more than the cluster size on your drive or partition, DOS or Windows allocates an entire cluster to hold this extra character. By simply dividing



this drive into two partitions, you can decrease the cluster size and therefore increase the actual amount of data that can be stored on this drive (as shown in the example of disk use by Microsoft Office in Table 2 on page 5).



This section provides a simple example of increasing the amount of data storage available on a hard drive by dividing it into two partitions. By creating more than two partitions on a drive, you may be able to increase the amount of data you can store even more.

To create an additional partition on a current drive:

- 1 Start Partition-It and click on the drive that you want to partition. Click the Details tab in the right pane of the Partition-It window if it is not already selected.

Disk usage information about that drive displays in the left pane of the primary Partition-It window. The Free Space figure in the Logical Information section shows the amount of free space available on that drive.

- 2 Compare the amount of free space on your drive against the values in Table 1 on page 4 to determine the size of the partition that you want to create.



If you do not have sufficient free disk space to create a new partition on your hard drive, you must either add another drive or delete some existing data or applications from your drive (be sure to back them up first). Partition-It can only create partitions in free space on a disk.

- 3 Select the **Resize** icon in the Partition-It toolbar or the **Resize** command from the Tools menu.

The Resize dialog displays.



If you want to resize the partition in which Windows is located, you will have to reboot your system so that Partition-It can automatically complete the operation in MS-DOS mode. Exit all Windows applications with open data files before modifying the partition on which Windows is located.

- 4 Drag the right border of the existing drive to the left, or use the up and down arrows to create free space equal to the partition size you identified in Step 2. Click **OK** to resize the existing partition and create free space on your drive.

The existing partition is resized and free space is created. The Resize dialog closes.

- 5 Select the newly-created free space in the left pane of the main Partition-It window, then select **Create** from the Tools menu.

The Create dialog displays.

- 6 Click **OK** to create a partition of the default (maximum) size.

A partition of the specified size is created.

That is all there is to it! By dividing your existing drive into multiple partitions, you can now make more efficient use of the storage available on that drive.

Changing the Cluster Size on Existing Partitions

As explained in "Introduction to Clusters and Cluster Size" on page 3, partitions of different sizes use different cluster sizes. Generally, selecting the smallest cluster size possible for a specific partition can both save disk space and improve performance. If a partition already uses the smallest possible cluster size for its size but you are very low on disk space on your ma-



chine, you may want to reduce the size of the partition first, enabling you to select a smaller cluster size. See Table 1 on page 4 for a list of partition sizes and corresponding cluster sizes.

In some cases, you may want to increase cluster size on a partition, depending on the type of data files it holds. For example, database files are typically accessed record by record—if the record size used in your databases is close to a larger cluster size, you may want to use the larger cluster size for the partition where those database files are stored. Similarly, multimedia files are typically very large, and are read sequentially, in their entirety. Increasing the cluster size on a partition where these are stored may also result in a performance improvement.


To change the cluster size of an existing partition:

- 1 In the main Partition-It window, use the mouse to select the partition in which you want to modify the cluster size.
The selected partition is highlighted.
- 2 Click the **Resize Cluster** icon in the Partition-It toolbar or the **Resize Cluster** command from the **Tools** menu.



*Under Windows 95, you can right-click in the left pane of the main Partition-It window to display a menu containing the **Resize Cluster** command.*

The Cluster Size dialog displays:



- 3 Unless you are creating a partition to hold database files with large record sizes or large multimedia files, let Partition-It automatically select the optimal FAT Type and Cluster Size for the selected partition by clicking **Optimal** and skipping to Step 8.

If you click **Optimal**, the **Space gained** item changes to show the free space you can regain by using the FAT type and cluster size that Partition-It selected for you.

- 4 If you want to select the FAT type of your partition manually, click on the **New FAT Type** selection box; otherwise, skip to Step 6.

A drop-down list displays your choices.



For more information on FAT types, see "Different Types of Partitions" on page 6.

- 5 Select the new FAT type.
The selected FAT Type displays in the **New FAT Type** selection box.
- 6 Click the **New Cluster Size** selection box.



A drop-down list displays your choices.



For more information on potential savings from different cluster sizes, see "Introduction to Clusters and Cluster Size" on page 3.

- 7 Select the new cluster size.

The selected cluster size displays in the **New Cluster Size** selection box. The **Space gained** item changes to show the free space you can gain by using the currently selected FAT type and cluster size.

- 8 Click **OK** to accept the FAT type and cluster size.

A dialog displays, showing the progress of Partition-It's changes to the selected partition. Once the FAT type and cluster size have been successfully modified on the selected partition, an **Operation Completed** dialog displays.

- 9 Click **OK** to close this dialog and return to the main Partition-It window.

Creating a Separate Partition for Virtual Memory Files



The process described in this section is an optional way of increasing performance on your system. We recommend that you have a basic knowledge of virtual memory concepts so you can understand the consequences of the changes you are making.

Microsoft Windows allows you to run multiple applications simultaneously, even though they may not fit into the amount of physical memory in your computer. To accomplish this, Windows uses a *swap file* (or *paging file* in Windows 95 terminology) on your hard drive as *virtual memory*. A swap or paging file is a file that Windows can use as a temporary location in which to save portions of the contents of system memory when other applications need more physical memory. The

size and location of this file is automatically specified by Windows, but can also be set by using:

- ▼ Windows 3.1x: the **Virtual Memory** option on the Control Panel's **386 Enhanced** item.
- ▼ Windows 95: the **Performance** tab's **Virtual Memory** dialog, located in the Control Panel's **System** option.

By default, your swap (or paging) file is a temporary file located on your boot drive that is recreated each time you start Windows. Since it takes time to create this temporary file each time you start Windows, creating a permanent swap file immediately improves system performance. Taking this one step further, you can usually obtain an additional performance improvement by putting this swap or paging file in its own partition. This can minimize the physical movement of the parts of your disk drive when Windows writes memory to disk.



Creating a separate partition for a Windows 3.1x swap file will almost always provide a noticeable performance increase. Creating a separate partition for your paging file under Windows 95 is less likely to provide a substantial performance increase, depending on the speed and size of the drive on which your swap file is located, as well as on the driver and interface used by that drive.

Extensive changes were made to swap file use and management between Windows 3.1x, Windows for Workgroups, and Windows 95. While Windows 3.1x and Windows for Workgroups use a swap file whose size is determined when you start Windows, Windows 95 uses a dynamic swap file whose size can change depending upon the number and sizes of the applications that you are running.



Before proceeding with the remainder of this section, make sure that you have sufficient space available on one of your disk drives to create a permanent swap partition. The size of your swap partition should be somewhere between one half and two and a half times the amount of physical memory in your computer. You should always locate your swap file on the fastest drive in your system.

Creating a Swap Partition Under Windows 3.1x

To create a separate swap partition under Windows 3.1x:

- 1 Close all open applications on your system and double-click the **Control Panel** icon in the **Main** program group. The Control Panel displays.

- 2 Double-click the **386 Enhanced** icon. The 386 Enhanced Control Panel option displays.

- 3 Click the **Virtual Memory** button. The Virtual Memory dialog displays.

- 4 Check the **Swapfile Settings** portion of the Virtual Memory dialog. If this indicates that you are using a **Temporary** or **Permanent** swap file on your boot drive, write down the current size of your swap file and skip to Step 12.

If you are using a permanent swap file on any disk other than your boot drive and creating the new swap partition will change the drive letter for this drive, you must continue to the next step so that you can create a temporary swap file located on the boot drive of your system.

- 5 Click the **Change** button to change the location and type of your swap file.

The **New Swapfile Settings** portion of the Virtual Memory dialog displays.

- 6 Click your boot drive in the **Drive** selection box.
- 7 Use the selection arrow to select **Temporary** from the **Type** selection box.
- 8 Either accept the suggested new size of your swap file in the **New Size** text entry box, or enter a new value. This value must be less than the amount of free disk space available on your boot drive. Write down the size of your swap file for future reference.

- 9 Click **Save**.

Windows displays a message stating that you must reboot your system to use the new virtual memory settings.

- 10 Click **Reboot now** to reboot your system. (You can click **Continue** if you need to save data in open applications before rebooting.)

Your system reboots.

- 11 Start Windows.
- 12 Start Partition-It, select your fastest disk drive from the drives list in the upper left corner of the Partition-It screen, and click on a free space area to use for your new swap partition.
- 13 Follow the procedure in "Creating a Partition" on page 39 to create the new swap partition. The size of this partition should be at least as large as the swap file size that you recorded in Step 4 or Step 8.
- 14 Double-click the **Control Panel** icon in the **Main** program group. The Control Panel displays.
- 15 Double-click the **386 Enhanced** icon. The 386 Enhanced Control Panel option displays.
- 16 Click the **Virtual Memory** button. The Virtual Memory dialog displays.



- 17 Click the **Change** button to change the location and type of your swap file.

The **New Swapfile Settings** portion of the Virtual Memory dialog displays.

- 18 In the **Drive** selection box, select the partition in which your new swap partition is located.

- 19 In the **Type** selection box, use the selection arrow to select **Permanent** as the swap file type.

Permanent displays in the swap file Type box.

- 20 In the **New Size** text entry box, enter the size of your new swap partition.

- 21 Click **Save**.

Windows displays a message stating that you must reboot your system to use the new virtual memory settings.

- 22 Click **Reboot now** to reboot your system. (You can click **Continue** if you need to save data in open applications before rebooting.)

Your system reboots. When your system restarts, you will be using the new partition for your swap file.

Creating a Swap Partition Under Windows 95

To create a separate swap partition under Windows 95:

- 1 Close all open applications on your system and select the **Control Panel** option from the **Start** button's **Settings** menu.

The Control Panel displays.

- 2 Double-click the **System** icon.

The System Properties Control Panel option displays.

- 3 Select the **Performance** tab.

The Performance tab displays.

- 4 Click the **Virtual Memory** button.

The Virtual Memory dialog displays. If the **Let Windows manage my virtual memory settings** button is selected, click **Cancel**, then click **Close** to close the System Properties item, close the Control Panel, and skip to Step 9.

- 5 Select the **Let Windows manage my virtual memory settings** button.

- 6 Click **OK** to accept the changes you have made.

Windows displays a message stating that you must reboot your system to use the new virtual memory settings.

- 7 Click **Reboot now** to reboot your system, or click **Continue** if you need to save data in open applications before rebooting.

Your system reboots.

- 8 Start Windows.

- 9 Start Partition-It, select your fastest disk drive from the drives list in the upper left corner of the Partition-It screen, and click on a free space area to use for your new swap partition.

- 10 Follow the procedure in "Creating a Partition" on page 39 to create the new swap partition. This partition should be at least as large as the amount of physical memory in your computer.

- 11 Reboot your system using the **Start** button's **Shutdown** option to ensure that the new partition is available.

Your system reboots.

- 12 Select the **Control Panel** option from the **Start** button's **Settings** menu.

The Control Panel displays.

- 13 Double-click the **System** icon.

The System Properties Control Panel option displays.



- 14 Select the **Performance** tab.
The Performance tab displays.
- 15 Click the **Virtual Memory** button.
The Virtual Memory dialog displays.
- 16 Select the **Let me manage my virtual memory settings** button.
- 17 Select the partition you just created in the **Hard Drive** selection box.
- 18 Specify a value one-half MB less than the size of the partition you just created as the maximum and minimum size of the swap file.
- 19 Click **OK** to accept the changes you have made.
Windows displays a dialog stating that you must reboot your system to use the new virtual memory settings.
- 20 Click **Reboot now** to reboot your system. (You can click **Continue** if you need to save data in open applications before rebooting.)
Your system reboots and runs with the new swap file.



Basic Partition-It Operations

In this chapter you will learn how to:

- ▼ Get information about disks and partitions on your system.
- ▼ Resize partitions.
- ▼ Create new partitions.
- ▼ Move partitions.
- ▼ Delete partitions.
- ▼ Move applications between partitions.

Getting Information About a Disk or Partition

Partition-It provides precise information about the hard drives in your system and the partitions located on those drives. If you are adding a new drive to your system, Partition-It can provide detailed information about the size and geometry of that drive. Partition-It can also help you identify bootable drives, determine where primary partitions are physically located, and determine the exact amount of available disk space available in different portions of your disk. Information about the physical location of partitions on your drives can be especially useful if problems develop with a particular head or disk surface. Advanced users may want to use this information to move partitions to safe locations on your disk.




The values displayed by Partition-It are more accurate than those shown by DOS utilities (such as FDISK) that round off the values they display.



To get information about a disk or partition:

- 1 In the left pane of the Partition-It window, click the disk or partition that you want information about.
- 2 Select the **Details** tab in the right pane of Partition-It's main window.

Information about the selected disk or partition displays in the right pane:



For more information about the values shown in Partition-It's Details window, see the online help.

Resizing a Partition

You may want to resize existing partitions for various purposes:

- ▼ freeing space so that you can create additional partitions
- ▼ making a partition smaller so that you can reduce the cluster size for increased data storage

- ▼ increasing the size of a partition that you use to hold large data files, where a larger cluster size may be more efficient for your applications.



If you plan to reduce the size of a partition, defragment it first, using Microsoft's Disk Defragmenter (DEFRAG.EXE). This will give you the most accurate picture of the minimum size required for a selected partition.



When you enlarge a partition and the new partition size requires a different FAT type or cluster size, Partition-It will automatically change them to the values required by DOS and Windows for the new partition. To override these changes when resizing a partition, see "Using the Advanced Resize Partition Dialog" on page 64.

To resize a partition:

- 1 In the main Partition-It window, use the mouse to select the partition you want to resize.

The selected partition is highlighted.




If you want to resize the partition on which Windows is located, you will have to reboot your system to let Partition-It automatically complete the operation from your system's MS-DOS mode. Exit all applications with open data files before resizing the partition where Windows is installed.

- 2 Click the **Resize Partition** icon in the Partition-It toolbar or select **Resize** from the Tools menu.

Partition-It displays its Scan dialog, which shows the progress of the automatic consistency check that Partition-It performs to verify the structure and consistency of the data on the selected partition.



Once this scan has completed, the Resize Partition dialog displays:



- 3 Enter the amount of free space you want to remain on either side of the partition you are resizing. You can use the up and down arrows on either side of the selected partition to change the amount of free space on either side of the partition, or just type numeric values in the text entry boxes. The red portion of the free space indicator shows the minimum size of the partition. The bright green area is the space currently allocated to the partition you are resizing.



You can also resize a partition by selecting either end of the graphical partition indicator and dragging it.

As you specify the free space size, the numbers in the Empty Space Left, (MB) and Empty Space Right, (MB) text boxes change, and the New Partition Size entry changes appropriately.



You cannot resize a partition below the size required to hold the data that it currently contains. You also cannot resize a partition beyond the boundaries of an adjacent partition.

- 4 Click **OK** to accept the currently displayed partition size



*You can click **Reset** if you want to restore the values shown when you first opened the Resize Partition dialog.*


A dialog displays as the partition is resized, and an Operation Completed dialog is displayed when the operation finishes.



Resizing a partition can take a bit of time, depending on the size and speed of the disk, the cluster size, and the original size of the partition you are resizing.

- 5 Click **OK**.

Partition-It's defragmentation dialog displays:



- 6 Click **Yes** to defragment the resized partition.



Defragmenting a partition is a good idea after you resize it. When data is moved to accommodate the new partition size, it can become fragmented.

Windows' Defragment Drive dialog displays. Follow the on-screen prompts to defragment the partition.

Creating a Partition

You will want to create partitions on disks that you have just added to your system or on existing disks after moving or decreasing the size of a partition.



To create a new partition, you must have free space on one of the disks in your system.



In terms of disk partitions, free space is a portion of the disk that is not currently allocated to a partition—it is not the same as unused space in an existing partition. If a portion of any of your disks is not allocated to a partition, it is shown in the left pane of the Partition-It window and is labeled “Free Space.”




To create free space on a disk, use Partition-It's Resize partition feature, as explained in “Resizing a Partition” on page 36. If all partitions are full on the disk where you want to create the new partition, use Partition-It's Move-It wizard to move applications to another disk, as explained in “Moving Applications” on page 46.

To create a new partition:

- 1 In the main Partition-It window, click the free space area in which you want to create the new partition.
The selected free space area is highlighted.
- 2 Click the **Create Partition** icon in the Partition-It toolbar, or select **Create** from the Tools menu.

The Create Partition dialog displays:



If you want to specify the FAT type or cluster size used when creating a partition, see “Using the Advanced Create Partition Dialog” on page 63 for more information.

- 3 In the **Label** text entry box, enter a name for the new partition. This name can be up to 11 characters long—if possible, use a name that indicates the purpose or contents of the partition.
- 4 Proceed to Step 5 if you want to allocate all available free space in the selected free space area to the new partition. To create a partition that uses only a portion of the available free space, use the up and down arrows or enter numeric values on either side of the graphical partition display to select the amount of free space you want to remain on either side of the partition you are creating.



You can also use the mouse to change the size of the new partition by selecting either end of the graphical partition display and dragging that end of the display to resize it.



As you specify the amount of free space, the graphical representation of the partition changes, the numbers in the Empty Space Left, (MB) and Empty Space Right, (MB) text boxes change appropriately, and the maximum size of the partition decreases.

- 5 To create the new partition as a primary partition, click the **Create as Primary** check box.



You can create the new partition as a primary partition if you currently have less than four partitions on your hard drive and the size of the new partition is less than one GB. For more information on partition types, see "Different Types of Partitions" on page 6.




*Selecting the **Create as Primary** check box will slightly increase the size of the new partition you are creating. Extended partitions require a small amount of additional space on the disk to store the extended partition boot record. On disks where only an extended partition has been created, this additional space is allocated at the beginning of the disk, in space that can only otherwise be used by a primary partition.*

- 6 Click **OK** to create the new partition using the information that is currently displayed.



*You can click **Reset** if you want to restore the partition size value shown when you first opened the Create Partition dialog.*

If creating the new partition has caused any existing drive letters to change, a warning displays:



- 7 Click **Yes** to restart your computer now.



*If creating a new partition has caused the letters associated with existing drives to change and you do not restart your computer at this point, it may be difficult to access applications on those drives, or those drives themselves, until you restart your computer. If the new drive letters conflict with any network drives that you previously mapped to drive letters on your system, Partition-It displays the label **Overlapped** beside the conflicting partition. You must re-map the network drives to other letters before you can use or modify the new partitions.*

Rules for Creating Partitions

You can only create four physical partitions on a disk, only one of which can be an extended partition. You can subsequently create additional logical partitions in the extended partition. However, if you try to create an additional partition on a drive that already has four partitions, and the partition you are trying to create is not adjacent to the extended partition, Partition-It will display an error message. To create additional partitions in this case, make sure that one of your partitions is an extended partition (created without the **Create as Primary** check box selected), and move partitions as needed to relo-



cate any free space on your disk so that it is adjacent to the extended partition. You can then create additional partitions in the extended partition. You can identify an extended partition by the dark border that surrounds it in the graphical view of your disk in Partition-It's main window.

Deleting a Partition

You may want to delete a partition for various reasons, such as to create free space for new partitions, or to remove partitions created for use with other operating systems (such as OS/2 or Linux) so you can partition them for use with Windows.



*When you delete a partition, all data on that partition is deleted. You can no longer access any files or data on that partition. Before deleting a partition, make **absolutely** sure that you do not need anything on that partition, or that you have a good backup of that partition.*


To delete a partition:

- 1 In the main Partition-It window, click the partition that you want to delete.

The selected partition is highlighted.

- 2 Click the **Delete Partition** icon in the Partition-It toolbar or select **Delete** from the Tools menu.

The Delete Partition dialog box displays:



- 3 If you are sure you want to delete this Partition, type the current label of the selected partition in the Enter Current Label text entry box and click **OK**. This is provided as a safety measure—the partition name is listed in the Current label field and as part of the Selected Partition field.

An Operation Completed dialog displays.

- 4 Click **OK** to return to the main Partition-It window.

Moving a Partition

You may want to move partitions to consolidate free disk space, usually after deleting or resizing another partition, so that you can create other partitions in this free space.


To move a partition:

- 1 In the main Partition-It window, select the partition you want to move.

The selected partition is highlighted.

- 2 Click the **Move Partition** icon in the Partition-It toolbar or select **Move** from the Tools menu.

The Move Partition dialog displays:





- 3 Enter the amount of free space you want to leave on either side of the partition you are moving. You can use the up and down arrows on either side of the selected partition or just type numeric values in the text entry boxes. The bright green area is the space currently allocated to the partition you are moving.



You can also move a partition by selecting the partition and dragging it to the location to which you want to move it.

As you modify the free space area, the numbers in the Empty Space Left (MB) and Empty Space Right (MB) text boxes change, and the New Partition Size entry changes appropriately.

- 4 Click **OK** to accept the new location of the selected partition.



*You can click **Reset** if you want to restore the values shown when you first opened the Move Partition dialog.*

An Operation Completed dialog displays when the operation finishes.



Moving a partition can take a bit of time, depending on the size and speed of the disk, the cluster size, and the amount of data in the partition you are moving.

- 5 Click **OK**.

The main Partition-It window displays.

Moving Applications

Partition-It's Move-It Wizard lets you move individual application or program groups from one partition to another. Common reasons for moving applications or groups of related applications are to:

- ▼ free disk space on selected partitions before resizing them
- ▼ relocate applications before deleting a partition that is otherwise unused
- ▼ better organize applications and data on your disks

Without Partition-It, moving an application would involve complicated and time-consuming steps such as trying to identify and locate all of the Dynamic Link Library (DLL) files used by that application and searching through initialization files and the registry to locate and modify all references to the location of that application.



To simplify moving an application, make sure that the application is not running and that any related functions in Windows 95's system tray or the Windows 3.1x desktop are closed or unloaded.

Partition-It's Move-It wizard easily moves applications from one partition to another, automatically relocating any resources required by the application and updating all references to that application in INI files and the Windows 95 registry. Move-It also automatically creates a compressed backup copy of the application before moving it and logs all changes to files related to the move, in case you encounter system problems (such as a power failure) while the application is being moved. The backup copy is deleted after the application has been moved successfully. If you subsequently decide to move the application to a different location, Move-It displays a dialog asking if you want to use the old log file to expedite the move.



The backup files created by moving an application are compressed, but in some cases may still require as much as 75% of the disk space taken up by the application itself. Before moving an application, make sure you have sufficient disk space.



TIP

If you want to move applications from the partition where Partition-It is installed and do not have much free disk space on that partition, you may want to change the location where Move-It creates its backup and log files, as explained in "Changing the Location of Move-It Backup Files" on page 66.

Move-It lets you move single applications or entire program groups or folders. Program groups or folders generally contain sets of applications that are installed together, and may share DLL files and a common directory location.



TIP

You should usually move an entire program group/folder together, rather than trying to move individual applications in that group/folder. You may not be able to move DLL files used by a single application because all of the applications in the group usually require many of the same DLL files. By default, Move-It will copy them instead of moving them. In the long run, this wastes disk space rather than conserving it.

To move an application:


- 1 Click the **Move Application** icon in the Partition-It toolbar.

Move-It begins scanning the hard drives in your system for applications and related files, displaying a status message as it scans your disks. Once Move-It finishes scanning, it also analyzes all files registered in the Windows shell, to ensure that it can subsequently update all references to them if you move them.



Scanning the drives in your system will take longer the first time you start Move-It, because Move-It saves a copy of this information. Subsequently, Move-It will use this information as a starting point each time you use it.

After Move-It finishes scanning your disks and Windows environment, the Select Application dialog displays:



The items shown in the Select Application dialog are:

- ▼ **Desktop** (Windows 95 only)—Applications whose icons are located on the desktop
 - ▼ **Start Menu** (Windows 95 only)—Applications whose icons and/or folders are located on the Start Menu.
 - ▼ **Programs without registered icons**—Windows applications that are not found in the Start Menu or any program group/folder.
 - ▼ **Programs with Log-It records**—Applications that you have already moved using Move-It, and whose backup files are still present on your system.
- 2 If you also want to scan network drives for DLL files and other files that may be related to any applications you move, select the **Select Network Drives** command from the **File** menu. By default, Move-It will only scan local




drives. If you do not want to scan any network drives, skip to Step 3.



You will want to scan network drives if any part of your system's Windows or Windows applications are located on a file server or other remote machine.

The Select Network Drive(s) dialog displays:



Select the network drives that you want to search by clicking their icons.

A check mark is displayed beside each selected drive.

Click **OK** to close the Select Network Drive(s) dialog.


The Select Network Drive(s) dialog closes, and Move-It scans any selected network drives. When the scan completes, the Select Applications to Move dialog displays.

- 3 If you want to view the icons for the items displayed in the Select Application to Move dialog, click the **Show program icons** check box.

If you checked **Show program icons**, all of the items in the Select Applications to Move dialog expand to show the icons for the programs they contain.

- 4 Navigate through the items displayed in the Select Application to Move list and select the application or program group/folder that you want to move.
- 5 Select the method that you want Move-It to use by clicking the button beside either the **Custom move** or **Express move** entries. The Custom method displays an additional dialog that lets you select and change the individual files that Move-It will move. The Express method automatically selects the files that will be moved.
- 6 If you want to limit the drives that Move-It searches when looking for DLL files that may be required by the application(s) you selected in Step 4, click the **Drive(s) to search** selection list. Move-It's default action is to search **All Drives** that it has scanned. If you are searching all drives on your system, skip to Step 8.

The Select Drive(s) to Search dialog displays:




- 7 Deselect those drives that you do not want to search by clicking on the check mark displayed to their left, and click **OK**.
- 8 Click **Next** on Move-It's Select Applications dialog.



Move-It begins scanning for files related to the application(s) you selected.


If you selected **Express** as the move method to use in Step 5, skip to Step 9. Otherwise, the Select Items dialog displays:



This dialog displays a list of each item that is associated with the application that you want to move. Items that Move-It identifies as safe to move are displayed with a green GO icon. Items that Move-It identifies as potentially unsafe to move are listed beside a yellow CAUTION icon. Items that Move-It identifies as unsafe to move are displayed with a red STOP icon. By default, only GO items will be moved.

Review the list and select any additional items that you want to move by clicking to the left of their icon. Deselect any items that you do not want to move by clicking on the check mark to the left of those items. Click **Next** to continue.

9 The Select New Location dialog displays:



- 10 In the Folders to be Moved section, select the folder that corresponds to the directory location of the application(s) that you are moving.

The selected folder is highlighted.

- 11 Enter the location to which you want to move the selected application in the Change to: field, or use the **Browse** button to select the new location.

- 12 Click **Next** to continue.

Move-It displays a confirmation dialog for each directory (folder) and subdirectory that will be moved.

- 13 Click **Yes** to confirm each folder that you want to move.



If you choose not to move a folder that is critical to the application you are moving, you may not be able to run the application after it has been moved.


A summary dialog displays, listing the number of folders that will be moved.

- 14 Click **OK** to continue.



Move-It begins scanning for files related to the application(s) you selected.


If you selected **Express** as the move method to use in Step 5, skip to Step 9. Otherwise, the Select Items dialog displays:



This dialog displays a list of each item that is associated with the application that you want to move. Items that Move-It identifies as safe to move are displayed with a green GO icon. Items that Move-It identifies as potentially unsafe to move are listed beside a yellow CAUTION icon. Items that Move-It identifies as unsafe to move are displayed with a red STOP icon. By default, only GO items will be moved.

Review the list and select any additional items that you want to move by clicking to the left of their icon. Deselect any items that you do not want to move by clicking on the check mark to the left of those items. Click **Next** to continue.

9 The Select New Location dialog displays:



- 10 In the Folders to be Moved section, select the folder that corresponds to the directory location of the application(s) that you are moving.

The selected folder is highlighted.

- 11 Enter the location to which you want to move the selected application in the Change to: field, or use the **Browse** button to select the new location.
- 12 Click **Next** to continue.
Move-It displays a confirmation dialog for each directory (folder) and subdirectory that will be moved.
- 13 Click **Yes** to confirm each folder that you want to move.




If you choose not to move a folder that is critical to the application you are moving, you may not be able to run the application after it has been moved.

A summary dialog displays, listing the number of folders that will be moved.


- 14 Click **OK** to continue.



Move-It's Review Item Selection dialog displays:



If any open files (such as DLL files that are currently running) are associated with the application you are moving, Move-It displays a warning dialog to let you know that such files exist and will not be deleted:



Open files are copied by Partition-It when an application is moved. The original copies of these files are deleted the next time you boot your system.

- 15 If the preceding dialog displays, click **OK** to continue.
- 16 Use the scroll bars in the Review Item Selection dialog to review all of the items that Move-It will move with the selected application. Click **Print** if you want to print a

copy of this information. To proceed with moving the application, click **Finish**.

Move-It displays three progress dialogs as it creates a compressed backup copy of your application, deletes the original application, and then moves the application to the new location using the backup copy.

The Move Complete dialog displays, listing the total number of items moved.

- 17 In the Move Complete dialog, click **OK** to return to the Select Application dialog. To see a listing of all of the items that were moved, click **Detail**.



*If you want to undo the move, click **Undo**, which restores the application to its original location and deletes the backup copies of the application you moved.*

If you selected **OK**, Move-It's Select Application dialog displays.

- 18 To move another application, return to Step 1 on page 48. To return to the main Partition-It window, click **Cancel**.



Advanced Operations

In this chapter you will learn how to:

- ▼ Create and use a recovery disk that can help you complete Partition-It operations that were in progress when a system failure occurred.
- ▼ Set advanced partition attributes.
- ▼ Use the advanced dialogs for Partition-It's Create and Resize operations.
- ▼ Change the location where Move-It stores its backup and log files.
- ▼ Use Partition-It on systems that run multiple operating systems.
- ▼ Use Partition-It with other disk compression and diagnostic utilities.

Creating and Using Partition-It Recovery Disks

No software package can prevent problems, such as power failures, that can damage your system if it is the middle of performing a complex operation such as moving or resizing partitions. To help eliminate the chance that such a failure could corrupt your system while Partition-It is running, Partition-It includes a DOS application, PARTDOS.EXE. This application enables you to complete most Partition-It operations that were interrupted by a system failure, and can usually prevent any loss of data or corruption of partition information.



To enable you to recover from system failures that occur when Partition-It is running, Partition-It offers to create a recovery disk during installation. This section explains how to create a recovery disk if you did not do so when you installed Partition-It. This section also explains how to use the recovery disk if a system failure occurs while using Partition-It.




We strongly suggest that you create a recovery disk for Partition-It before using any Partition-It functions. If you experience a system failure while using any Partition-It operation, you must not let your system restart from the hard drive. Turn your machine off, locate the Partition-It recovery disk, and restart your system from the floppy disk.

To create a recovery disk if you have not already done so:

- 1 Click the Tools menu and select **Recovery Disk**.
The Recovery Disk dialog displays.
- 2 Insert a floppy disk into drive A: on your system, and click **Yes**.

The Format Partition-It Recovery Disk dialog displays:



- 3 Select the way in which you want to format the floppy disk:

- ▼ **Quick** erases all of the files on the floppy disk without reformatting it.
- ▼ **Full** completely reformats the floppy disk. You will need to do this if the disk is not already formatted.
- ▼ **Use free space** adds Partition-It's recovery files to any files that are currently on the floppy disk. If you do not have sufficient free space on the disk for these files, an error dialog displays, and you will have to select one of the other two options to proceed.

- 4 Click **OK**.

The recovery disk is created. Label the disk "Partition-It Recovery Disk" and put it in a safe place.

To use a Partition-It recovery disk if a system failure occurs:

- 1 Insert the Partition-It recovery disk in the main floppy drive for your system.
- 2 Reboot your system.
- 3 If the PARTDOS application does not start automatically, type PARTDOS at the DOS command-line prompt.
The PARTDOS application completes the operation that was in progress when the system failure occurred.
- 4 When the PARTDOS application finishes, exit from the application, remove the recovery floppy from the floppy drive, and reboot your system normally.

Setting Advanced Partition Attributes

Partition attributes are settings that determine how your system displays and uses each partition. This section explains how to use Partition-It to set the most important partition attributes. Besides the partition type, the most commonly-used partition attributes are:

- ▼ **active**—whether a primary partition is one that you can boot from.



- ▼ **shown/hidden**—whether a partition is visible to DOS or Windows applications.

You can have up to four physical partitions on a hard disk (one of which can be an extended partition), but only one of these is active at a given time. Your computer identifies the active partition from your hard drive's master boot record (MBR), and boots from this partition when you start your computer.



For more information on partition types, see "Using Other Types of Partitions" on page 8.


Hiding a Partition

You may want to hide a partition to store data that you do not want casual users of your machine to see, or to reserve disk space for future expansion.

To hide a partition:

- 1 In the left pane of the main Partition-It window, select the partition you want to hide.
- 2 Select **Hide** from the Tools menu.

The Hide Partition dialog displays:



- 3 Enter the label for the partition and click **OK**.

The selected partition is marked as hidden. This partition will not be visible in Windows 95 after you reboot your system. The icon for this partition displays the letter **h** to indicate that it is hidden.

Making a Hidden Partition Visible

As you need to use more of the disk space on your computer, you may want to "un-hide" a partition that you had previously marked as hidden.

To make a hidden partition visible to the system:


- 1 In the left pane of the main Partition-It window, select the hidden partition you want to make visible.

- 2 Select **Unhide** from the Tools menu.

A message displays, stating that the partition will only be visible after you restart Windows 95.

- 3 Click **OK**.

The Unhide Partition dialog displays:



- 4 Enter the label for the selected partition and click **OK**.

The selected partition is unhidden. A drive letter will be assigned to this partition and the partition will be visible to DOS and Windows applications the next time you start Windows 95.

Marking a Partition as Active

An active partition is one that your computer can boot from. If you are experimenting with or using multiple operating sys-



tems on your computer, you may want to mark a partition as active to boot from it or for testing purposes.




Some operating systems (such as OS/2) have problems with multiple partitions that are marked as active. If you are marking a new partition as active, make sure that you either have another bootable partition or that you install a bootable version of your operating system in the new active partition.

To mark a partition as active:

- 1 In the left pane of the main Partition-It window, select the partition you want to mark as active. This must be a primary partition—extended partitions cannot be marked as active.

- 2 Select **Set Active** from the Tools menu.

The Set Active Partition dialog displays:



- 3 Enter the label for the selected partition and click **OK**.

The selected partition is marked as active, and will be examined for bootable information the next time you start Windows.

Using Partition-It's Advanced Dialogs

Partition-It provides advanced Create and Resize Partition dialogs that enable you to specify the FAT type and cluster size used when partitions are created or resized. You may want to override the default FAT type and cluster size if you plan to use

the new or resized partition for a specific purpose, such as holding large database or multimedia files where reading and writing larger amounts of data may provide a performance improvement.



For more information on cluster sizes and their implications on a disk partition, see "Introduction to Clusters and Cluster Size" on page 3. For more information on FAT types, see "Different Types of Partitions" on page 6.


Using the Advanced Create Partition Dialog

To display the Advanced Create Partition dialog instead of the standard Create Partition dialog, select the **Advanced Dialogs** option from the **Preferences** menu before selecting the **Create** command.

To specify the FAT Type or Cluster Size used when creating a partition:

- 1 Select **Advanced Dialogs** from the Preferences menu.
- 2 Select **Create** from the Tools menu.

The Advanced Create Partition dialog displays:





- 3 Select the free space area in which you want to create the new partition, as explained in "Creating a Partition" on page 39.

- 4 Clear the **Auto size cluster** check box.

The **New FAT Type** and **New Cluster Size** options activate.

- 5 To specify the FAT Type for the new partition, click **New FAT Type** and select the FAT type you want to assign to the partition.

A pop-up list displays, giving the FAT types that are valid for the new partition. If only one FAT type is valid, only one value displays. The selected FAT type value displays in the **New FAT Type** entry box.

- 6 To specify the cluster size for the new partition, click **New Cluster Size** and select the cluster size you want to assign to the partition.

A pop-up list displays, giving the cluster sizes that are valid for the new partition. If only one cluster size is valid, only one value displays. The selected cluster size value displays in the **New Cluster Size** entry box.



*If you modify the default FAT type and cluster size values selected by Partition-It and then change your mind, you can restore these default values by clicking the **Reset** button.*

- 7 Click **OK** to create the partition with the selected FAT type and cluster size values.


Using the Advanced Resize Partition Dialog

To display the Advanced Resize Partition dialog instead of the standard Create Partition dialog, select the **Advanced Dialogs** option from the **Preferences** menu before selecting the **Resize** command.

To specify the FAT Type or Cluster Size used when resizing a partition:

- 1 Select **Advanced Dialogs** from the Preferences menu.
- 2 Select **Resize** from the Tools menu.

The Advanced Resize Partition dialog displays:



- 3 Select the new size for the partition as explained in "Resizing a Partition" on page 36.
 - 4 Clear the **Auto-Resize Cluster** checkbox.
- The **New FAT Type** and **New Cluster Size** options activate.
- 5 To specify the FAT Type for the resized partition, click **New FAT Type** and select the FAT type you want to assign to the partition.

A pop-up list displays, giving the FAT types that are valid for the new size of the partition. If only one FAT type is valid, only one value displays. The selected FAT type value displays in the **New FAT Type** entry box.

- 6 To specify the cluster size for the resized partition, click **New Cluster Size** and select the cluster size you want to assign to the partition.



A pop-up list displays, giving the cluster sizes that are valid for the new size of the partition. If only one cluster size is valid, only one value displays. The selected cluster size value displays in the **New Cluster Size** entry box.



*If you modify the default FAT type and cluster size values selected by Partition-It and then change your mind, you can restore these default values by clicking the **Reset** button.*

- 7 Click **OK** to resize the partition with the selected FAT type and cluster size values.

Changing the Location of Move-It Backup Files


While moving applications, Move-It automatically creates a compressed backup copy of the application before moving it and creates a log file listing all changes to files related to the move. These files are created in case you encounter system problems (such as a power failure) while the application is being moved. The backup copy is deleted after the application has been successfully moved, but can temporarily require up to 75% of the disk space required by the application you are moving.

If you want to move applications from the partition where Partition-It is installed and do not have much free disk space on that partition, you may want to change the location where Move-It creates its backup and log files. By default, Move-It stores these files in the BACKUP subdirectory of the directory where you installed Partition-It. Changing the location where Move-It creates these files enables you to store them on a disk or partition where you have sufficient free space.

To change the location of Move-It backup and log files:

- 1 Click the **Preferences** menu and select **Move-It Setup**.

The Move-It Default Settings dialog displays:



- 2 Enter the drive letter and full pathname of the new location where you want to store Move-It's backup and log files, or use the browse buttons to select the new drive and pathname.
- 3 Click **OK** to save the new location(s).

Hardware Issues for Partition-It

If any of the drives in your system were created using your BIOS's LBA mode, changing your system setup to disable LBA mode may cause partitions on those drives to be inaccessible.

Using Partition-It With Other Operating Systems

Partition-It cannot directly modify non-FAT partitions used by other operating systems. This section explains some issues you must take into account if you are running multiple operating systems on your PC and are using Partition-It.



If your system can boot multiple operating systems ("dual boots"), we strongly recommend that you do not add or delete partitions with lower drive letters than any existing, bootable partitions on your machine.

Using Partition-It on Systems That Also Run Windows NT

Windows NT uses a hidden file called BOOT.INI, located in the root directory of your system's boot drive, to determine which operating systems are available and identify the partitions where they are located. Windows NT also stores information about installed application in the NT registry. Windows NT assigns drive letters differently than DOS, Windows 3.1x, or Windows 95, and uses numeric identifiers for partitions in these files rather than using drive letters. Because Partition-It cannot always access these files (such as when they are located in NTFS partitions), creating or deleting partitions with a lower drive letter than a bootable NT partition may cause you to have to re-install NT and your applications.

Using Partition-It on Systems That Also Run OS/2

When booting OS/2, the Boot Manager looks for a specific partition letter, as defined using the OS/2 FDISK utility. If you move an OS/2 boot partition, its entry is cleared from the OS/2 Boot manager menu until the drive letters are resynchronized.

To resynchronize OS/2 partition identifiers:

- 1 Reboot OS/2 from the installation disks.
- 2 Run the FDISK utility from the final OS/2 installation disk.
- 3 Select the OS/2 boot partition and choose **Add to Boot Manager menu** from the FDISK options menu.

- 4 Reboot your system to verify that OS/2 can find the relocated boot partition.

Using Partition-It with other Utility Programs

Partition-It modifies your system at a very low level, and may interact with other low-level applications such as virus-scanning and disk-monitoring software. This section discusses how Partition-It interacts with other disk utilities, such as virus checkers, software that verifies the structure of your hard drive, and various disk compression utilities.

Anti-Virus Software

Many anti-virus software packages, such as those from Central Point Software, Norton, and McAfee, interpret any change to the partition tables on your system as evidence of a possible virus. These applications are designed to be super vigilant, so you should always instruct these applications to re-examine your hard drives after creating, deleting, or resizing partitions using Partition-It. This guarantees that these packages will recognize and accept any changes you made using Partition-It.

Anti-virus software packages may also display messages when Partition-It updates the partition information stored in the master boot record on your system's boot drive. If such messages display, simply continue—do not repair or reject Partition-It's changes. Doing so may over-write or destroy the changes you have just made to your disk using Partition-It.

Norton Disk Doctor and Norton Anti Virus

Norton Disk Doctor and Anti Virus software save a copy of your system's master boot record (MBR) to enable you to recover from viruses or other forms of disk corruption. After using Partition-It to make changes to the partitions on your system and rebooting your computer, Norton Disk Doctor and Anti Virus will detect the changes to the MBR and partition table as a potential virus or corruption. Do *not* attempt to repair

these changes or revive the old MBR or partition table. See the next sections for specific information on using Partition-It with these packages.

Norton Anti Virus (NAV)

After your reboot your system, NAV displays a message indicating that "The master boot record of drive X: has changed since inoculation" (where X: is the letter of the partition that was modified by Partition-It). NAV displays the following options: REPAIR, INOCULATE, or CONTINUE.

You **must** select INOCULATE to cause NAV to accept the changes made by Partition-It. This also causes NAV to update its copy of the MBR and partition table to reflect the changes made by Partition-It.



***Do not select REPAIR!** Selecting NAV's REPAIR option will destroy Partition-It's changes to your disk and result in data loss.*

Do not select CONTINUE, because this will only bypass the problem for the current session. The next time you reboot your system, NAV will display the same REPAIR, INOCULATE, or CONTINUE message. You should choose INOCULATE if you see this message again.

Norton Disk Doctor (NDD)

After rebooting your system, NDD displays the following message: "A DOS partition has been found, but DOS currently can't access it. If you are unable to access a disk that you previously could, you should revive this partition. Would you like to revive this partition? Yes or No."

1 Select **NO**.

The following message displays: "Partition Search. You have chosen not to revive the partition. Do you want Norton Disk Doctor to mark the partition so it doesn't ask about it again? Yes or No."

2 Select **YES**.

A dialog displays the message: "Create Undo File. The Norton Disk Doctor is about to make changes to your disk. You may wish to create an Undo file so that changes can be undone... Create Undo File, Skip Undo File, or Exit."

3 Select **SKIP UNDO FILE**.

The following message displays: "If you wish to undelete this partition at a later time, use the /UNDELETE switch when starting NDD. OK."

4 Select **OK**.

The following message displays: "Partition information has been changed. In order for the new changes to take effect, your computer must be restarted. After the computer is restarted... Would you like to restart your computer?"

5 Select **RESTART YOUR COMPUTER**.

NDD updates its files and reboots your computer.

Stacker

Partition-It does not conflict with Stacker and similar software packages (such as DiskSpace and DriveSpace), but cannot directly increase the amount of disk space available to these utilities. These disk compression software packages create compressed files that DOS and Windows can use as virtual partitions. These files are located on existing DOS physical partitions. Since virtual partitions use customized algorithms to allocate and use disk space, they let you store large amounts of data in small partitions.

Since Stacker "partitions" are actually files that are located in FAT partitions, you can only use Partition-It to increase the size of the physical partitions in which stacked drives are located. You can then subsequently use Stacker to increase the size of the virtual partition, since the physical partition is now



larger. Partition-It does not let you resize Stacked partitions directly, because they are not real partitions.



Quarterdeck Technical Support

Your Quarterdeck software comes with three months of prepaid VIP technical support. Your prepaid VIP support starts on your first technical contact with our Technical Support department. When you contact us, we will give you a VIP identification number for future technical support calls.

To be eligible for continued support beyond your first contact, please send us your product registration card, which serves as proof of ownership for a current version of a Quarterdeck product.

1-800-ROBOTECH—Free automated support

For fast, free support, try our toll-free, automated technical support information system, 1-800-ROBOTECH. You'll get the most out of Quarterdeck products, gain more memory, and learn hot tips and tricks. Navigation is easy—just listen to the instructions that tell you what keys to press for the kind of help you need.

1-800-ROBOTECH is available 24 hours a day, 7 days a week, including holidays. Just dial **1-800-ROBOTECH (1-800-762-6832)** from a touchtone phone.

Q/FAX—Technical Bulletins and Product Information by Fax

Q/FAX is Quarterdeck's free, 24-hour, outbound automated fax service featuring receive technical bulletins, product information, and upgrade notices. To use Q/FAX, call **(800) 371-4566** or **(573) 499-4556** and follow the voice menu.



Quarterdeck Bulletin Board System

Our BBS provides access to all technical notes, product and upgrade bulletins, patch files, and user-uploaded utility programs relating to our products. Call (573) 875-0503. Set your modem for 8-bit word length, no parity, and 1 stop bit.

Talk to a Technical Support Representative

To talk to a technical support representative, call us at (573) 875-0932. Please have your Quarterdeck customer VIP number or product serial number available. If possible, please be at your computer when you call.

Online Technical Support via CompuServe

Quarterdeck's CompuServe forum maintains a complete library of technical bulletins, compatibility updates, and enhancement utilities. In addition, the extensive public discussion area is full of great tips and tricks. From within CompuServe, type **GO QUARTERDECK**.

Quarterdeck offers an introductory membership to CompuServe that includes ten free hours of use and a complimentary subscription to CompuServe magazine. To obtain your introductory membership, just call (800) 524-3388. Ask for representative #372.

Quarterdeck's World Wide Web Site

To get to our home page, just point your Web browser at:

<http://www.quarterdeck.com/>

Quarterdeck's FTP Site

To reach our FTP site, FTP to **quarterdeck.com**, log in as **anonymous**, and use your e-mail address as the password. You can obtain a list of files available for FTP access by downloading the README file from `~/pub`.



Glossary

A

active partition

A partition from which DOS or Windows can boot.

B

boot information

Information used by an operating system to start that operating system from a disk or partition.

boot manager

An OS/2 application that enables you to select from a list of bootable partitions.

bootable partitions

A partition that contains the information necessary to start a specific operating system.

C

cluster

The smallest unit of disk space that can be allocated to a file in a FAT file system. The size of a cluster is determined by the type of partition on which a file is located and the size of that partition. See: FAT file system, cluster size, partition type, partition size

cluster size

The size of the smallest amount of disk space that can be allocated to a file on a partition. The cluster size is determined



by the partition type and partition size, as shown in the following table for cluster sizes on a FAT-16 partition:

Table 5: Partition and Cluster Sizes

PARTITION SIZE	CLUSTER SIZE
1 - 31 MB	512 byte
32 - 63 MB	1 K
64 - 127 MB	2 K
128 - 255 MB	4 K
256 - 511 MB	8 K
512 - 1023 MB	16 K
1024 - 2047 MB	32 K

D

DLL

Dynamic Link Library: a file containing program code that performs functions that can be used by one or more Windows applications.

drive

A storage device that is present in your system. Drives can be removable (floppy disks, ZIP drives, Bernoulli drives, etc.) or fixed. Partition-It only manages fixed drives. See: fixed drives

drive letter

A letter (e.g., C:) that uniquely identifies a physical or logical partition to an operating system.

dual boot

A system that is configured to start one of multiple operating systems.

E

extended partition

A physical partition on your hard drive that can contain one or more logical partitions. See: logical partition, partition

extended partition boot record

The portion of a hard drive that DOS/Windows allocates to hold information about the partitions located within an extended partition. This space is allocated at the beginning of any hard drive that contains extended partitions.

F

FAT

File Allocation Table: the construct used by DOS/Windows systems to locate files and free space within a partition. See: file systems, FAT file systems

FAT file system

Formatted partitions that use a FAT to track the allocation of space to files and directories. See: FAT, FAT-12, FAT-16, FAT-32, file systems

FAT 12

A FAT partition that uses 12-bit records to store information about the location of blocks associated with files on that partition. FAT 12 partitions can be from zero to 32 MB in size.

FAT 16

A FAT partition that uses 16-bit records to store information about the location of blocks associated with files on that partition. FAT-16 partitions can be up to one GB in size.

FAT 32

A FAT partition that uses 32-bit records to store information about the location of blocks associated with files on that partition. FAT 32 partitions can be any size up to $(2^{32}-1)K$.



NOTE: The FAT 32 partition specification was not available from Microsoft at the time that this manual went to press.

FDISK.EXE

The DOS/Windows utility provided to create partitions. This utility does not provide the ability to modify partitions without deleting and recreating them.

file systems

Once a partition is allocated, the storage associated with that partition must be formatted in a way that it can be used by an operating system. DOS and Windows systems format partitions using the FAT file system. Other operating systems use other partition types that are optimized for those operating systems—for example, OS/2 uses a file system type known as HPFS (High Performance File System) and Windows NT uses a file system type known as NTFS (NT File System). See: FAT file system

fixed drives

Drives whose storage media cannot be removed from your system. Frequently referred to as *hard drives*.

formatted partitions

Partitions that have been “pre-processed” to be able to record information as required by a specific operating system.

free space

In Partition-It, this is a portion of your hard disk that is not currently allocated to a partition.

H

hard drive controller

The system hardware that manages access to your hard drives. This hardware may be a card in a slot in your PC or can also be integrated into your system's primary circuit board.

hard drives

Storage devices that cannot be removed from your system.

hidden partition

A partition to which disk space is allocated but which is not visible to DOS/Windows applications.

HPFS

High Performance File System, the OS/2 file system.

I

IDE

Integrated Drive Electronics: a mechanism implemented in hardware to integrate some functions of the hard drive controller into the hard drive itself.

L

LBA

See: logical block addressing

logical block addressing

A method used by some system BIOS's to extend the standard cylinder/head/sector block location mechanism in order to support larger drives and partitions.

logical partition

A contiguous portion of an extended partition on your hard drive that can be used by your operating system as a partition. See: extended partition, partition

M

Master Boot Record

The first sector of a hard disk, used to store information about the partitions on that disk. If any partition on that disk is active, the MBR also stores boot information. See: active partition, boot information

MBR

See: Master Boot Record



N

NTFS

NT File System, the Windows NT file system.

P

partition

A portion of your hard drive that DOS or Windows can address using a letter.

partition size

The amount of disk space associated with a partition. The size of a partition determines the maximum cluster size used in that partition. See: cluster size, clusters

physical partition

A partition that occupies a physical portion of your hard drive. See: logical partition, extended partition

primary partition

A physical partition on your hard drive that is not an extended partition (and which therefore does not contain any logical partitions).

S

storage media

The physical surfaces where information is stored on storage devices in your system. See: hard drives



Index

A

- active partition 59
- anti-virus software 69
- applications
 - moving 46

B

- Boot Manager menu 68
- boot problems 57
- BOOT.INI file 68

C

- Central Point virus checker 69
- changing drive letters 43
- clusters
 - definition 3
- colors
 - partitions and icons 20
- creating partitions 40
 - rules for 43

D

- deleting partitions 44
- Desktop
 - in Move-It 49
- disk space requirements 11
- disks
 - displaying 19
 - getting information about 36

E

- extended partition boot record 42
- extended partitions 7
 - extra space required by 42
 - graphical display of 20

F

- FAT 32
 - availability 8
- FAT file systems 7
- FAT-12 7
- FAT-16 7
- FAT-32 7
- file allocation table 7
- file system
 - definition 3
- fragmentation
 - definition 9
- free space
 - calculating 35
 - definition 40
 - discrepancies in 42

G

- graphical view 19
 - of extended partitions 20

H

- hardware requirements 11
- hidden partitions 60



hiding a partition 60
 unhiding 61
HPFS partitions 68

L

LBA mode 67
logical block addressing 67
logical partitions 7
Log-It records 49

M

master boot record 60
McAfee anti-virus software 69
moving
 partitions 45
 moving applications 46

N

network drives
 changing drive letters 43
 scanning 49
Norton Anti-Virus 69
Norton Utilities 69
NTFS partitions 68

O

OS/2 68
overlapped drives 43

P

paging file
 definition 28
Partition-It
 features and benefits 1
 system requirements 11
partitions
 active 59
 creating 40
 definition 2
 deleting 44
 displaying 19

 extended 7
 getting information about 36
 hidden 60
 hiding 60
 logical 7
 moving 45
 NTFS 68
 primary 7
 resizing 36
 showing 61
 shown 60

 primary partition 7
 Programs with Log-It records
 in Move-It 49
 Programs without registered
 icons
 in Move-It 49

R

recovering from system failures
 57
recovery disk
 creating 58
 using 59
resizing partitions 36
rules for creating partitions 43

S

scanning
 local drives 48
 network drives 49
 selected drives 51
showing a hidden partition 61
Stacker 71
Start Menu
 in Move-It 49
starting Partition-It 15
Support, technical
 see technical support
swap file
 definition 28

 separate partition for
 Windows 3.1x 30
 separate partition for
 Windows 95 32

system area 47
system failures
 recovering from 57
system requirements 11
system tray 47

T

Technical support
 BBS 74
 fax 73
 FTP 74
 telephone 73, 74
 World Wide Web 74
tree view 19
 definition 19

U

unhiding a partition 61

V

virtual memory
 definition 28
virus checking software 69

W

Windows NT 68


3.5" Diskette Replacement Order Instructions


If you do not have a CD-ROM drive, 3.5" diskettes are available for Partition-It. Separate disk sets are available for Windows 3.1 and Windows 95. The total charge for the diskettes, including shipping and handling, is \$5.95 per set. This offer is valid in the U.S. only and is only available to registered users of Partition-It.


Should you need diskettes for Partition-It, please call 1-800-683-6696 and a product consultant will be happy to assist you. You will need to specify whether you are using Windows 3.1 or Windows 95. The When the product consultant asks you for an offer code number, use **#03504**.

Thank you for your continued support.

Quarterdeck Corporation









Quarterdeck Corporation 13160 Mindanao Way, Marina del Rey, CA 90292-9705
Product Information: (800) 683-6696 FAX: (813) 523-2391 info@quarterdeck.com
Technical Support Information: See Appendix A of this guide.
World Wide Web: <http://www.quarterdeck.com/>

PLACE
STAMP
HERE

Quarterdeck Corporation
P.O. Box 18049
Clearwater, FL 34622



IMPORTANT: REGISTER TODAY!

GET 90 DAYS PREPAID TECHNICAL SUPPORT

Return this card to get prepaid support for 90 days from the date of your first call.

As a registered Quarterdeck software user you'll enjoy these advantages: access to Technical Support Services, advance notification of upgrades, special offers on Quarterdeck products, and specific product information sent only to registered users.

To register, just complete the postage-paid registration card below and drop it in the mail, or fax it to us at 573.875.0595. We'll add you to our list of registered users. All we need is your name, address and phone number. It's that easy.

SERIAL # PIWU1000108809

Complete this simple registration form to enter the monthly drawing for Quarterdeck's entire retail line of Utility and Internet software!



Every month, we'll select four new registered customers to receive over \$4,000 worth of Quarterdeck Utility and Internet software, including award-winning titles like QEMM®, CleanSweep®, MagnaRAM™, WebSTAR™, WebCompass™, PROCOMM® and Hijaak®! All winners will be notified by phone. So go ahead and enter today!

**PARTITION - IT
Version 1.0**

YES! Please add my name to your list of registered users.

PLEASE PRINT CLEARLY OR TYPE

FIRST NAME		M.I.	LAST NAME	
COMPANY NAME				
ADDRESS				
ADDRESS				
ADDRESS				
CITY				STATE/PROV.
COUNTRY				ZIP/POSTAL CODE
AREA/CNTRY. CODE	DAYTIME PHONE	EXTENSION	AREA/CNTRY. CODE	FAX NUMBER
EMAIL ADDRESS				

What is the primary use of this computer?

- ☐ Business/Corporate (100 or more employees)
- ☐ Business/Corporate (under 100 employees)
- ☐ Home Office/Small Office
- ☐ Personal Home Use
- ☐ Government
- ☐ Education

How much memory (RAM) does your computer have?

- ☐ 4-8 Mb
- ☐ 9-16 Mb
- ☐ 17-32 Mb
- ☐ Over 32 Mb

Do you own a CD-ROM? ☐ Yes ☐ No

Are you connected to ☐ Local Area Network ☐ Internet?

Which operating system(s) are you currently using?
(Check all that apply)

- ☐ Windows 95
- ☐ Windows 3.x
- ☐ Windows NT
- ☐ Macintosh
- ☐ Unix
- ☐ Other

What feature(s) would you like to see added to this product?

SERIAL # PIWU1000108809





NO POSTAGE
NECESSARY
IF MAILED
IN THE
UNITED STATES

BUSINESS REPLY MAIL

FIRST CLASS MAIL

PERMIT NO. 62

COLUMBIA, MISSOURI

POSTAGE WILL BE PAID BY ADDRESSEE

QUARTERDECK CORPORATION
PO BOX 1471
COLUMBIA MO 65205-9981

